1

Global and Synoptic Scale Circulation Systems

Poleward energy transport on a rotating sphere

Hadley cells and Ferrel cells


Polar vortex and midlatitude jet streams


Midlatitude cyclones as waves

The circulations of the atmosphere and oceans are ultimately driven by solar and longwave radiation imbalances Balance Balance 379 37° Deficit Deficit Surplus Radiant energy in one vear Heat Heat transfer transfer 90 60 30 0 30 60 90 °North Latitude °South

If the Earth didn't rotate, it would be easy for the flow of air to balance the energy • Thermal

- convection leads to formation of convection cell in each hemisphere
- Energy transported from equator toward poles
- Surface wind in Colorado would always blow from the North







Key Features of Global Circulation

- Hadley cell (thermally direct cell)
- driven by N-5 gradient in heating
- air *rises near equator and descends* near 30 degrees
- explains deserts; trade winds; ITCZ
- Ferrel Cell (indirect thermal cell)
- driven by heat transports of *eddies*
- air *rises near 60 degrees* and descends near 30 degrees
- explains surface westerlies from 30-60
- Weak winds found near
 - Equator (doldrums)
 - 30 degrees (horse latitudes)
- Boundary between cold polar air and mid-latitude warmer air is the *polar front*










CSU



- 1. Driven by differential solar heating between the equator and poles. Atmospheric general circulation acts to move heat poleward.
- 2. In Hadley cell, warmer air rises and moves poleward. Equator-to-pole Hadley cell is impossible in the presence of rotation
- 3. In the Northern Hemisphere, air is deflected to the right as it moves; in the Southern Hemisphere, it is deflected toward the left.
 - rotation produces trade winds; surface westerlies in NH; upper tropospheric jets.
- 4. Ferrel cell is the "zonal mean" response to poleward heat and momentum fluxes by eddies. It runs backwards! Transports heat the wrong way!








Sources of Atmospheric Water


- Water vapor is concentrated in the tropics
- Evaporation from the sea surface depends on radiation, humidity, and wind
- The greatest water source is in the *subtropics*, with near zero evaporation in the ITCZ



Energy in the Global Atmosphere


Name	Symbol	Formula	Amount $\times 10^{6}$ J m ⁻²	% of total
Internal energy	IE	$c_{\nu}T$	1800	70
Potential energy	PE	gz	700	27
Latent energy	LH	Lq	70	2.7
Kinetic energy	KE	$\frac{1}{2}(u^2+v^2)$	1.3	0.05
Total energy	IE + PE + LH + KE		2571	100

- Four kinds of energy: heat/enthalpy and gravitational potential account for 97%
- Kinetic energy is small but very important for moving the others around!
- Much of the energy is unavailable for conversion (atmosphere "holding itself up")
- Circulation responds to energy (temperature) gradients on constant pressure surfaces




Baroclinicity and the Polar Front Jet


Warm




Cold





- Warm air occupies more vertical space per mass (pressure depth)
- Tilt of pressure surfaces increases with height
- Coriolis force produces wind flow into screen
- Wind max (jet stream) occurs above steepest temperature gradient







- Eddies (storms) transfer momentum poleward in the upper troposphere.
- This momentum transfer weakens the Hadley circulation, but drives the Ferrel cell.






CMMAP







Atmospheric Circulation in a nutshell

- Hot air rises (rains a lot) in the tropics
- Air cools and sinks in the subtropics (deserts)
- Poleward-flow is deflected by the Coriolis force into westerly jet streams in the temperate zone
- Jet streams are unstable to small perturbations, leading to huge eddies (storms and fronts) that finish the job